



FitronTP – Update der Software

Voraussetzungen:

Sie benötigen einen USB Speicherstick (max. 4GB). Auf diesem muss sich ein Verzeichnis mit dem Namen "FitronTPUpdate" befinden. Darin muss sich die eigentliche Updatedatei mit dem Namen "FitronTPUpdate.zip" befinden.



Diese Datei haben Sie ggf. von unserem Service per E-Mail erhalten.

Schalten Sie das Gerät aus und stecken Sie den USB Speicherstick in den USB Anschluss auf der linken Seite der Gerätefront. Schalten Sie das Gerät nun ein. Wenn das Update auf dem USB Speicherstick erkannt wurde, erscheint folgender Hinweis: "**Software update found on USB stick**"



Drücken Sie nun den Button mit der Beschriftung "start update".

FitronTP Update	
Installed version: 1.0.3.0 Source path: \Program Files\FitronTP\Update Destination path: \Program Files\FitronTP	
Status:	
(c) 2013 by Fiege Electronic GmbH	
start Update	Exit

Auf dem folgenden Bildschirm drücken Sie nun den Button mit der Beschriftung "start Update".





FitronTP – Update der Software

Das Update wurde vollständig ausgeführt, wenn im Statusfenster die Meldung "**Update done**" erscheint.

Installed version: 1.0.3.0 Source path: \Program Files\FitronTP\Update Destination path: \Program Files\FitronTP. Status: Copy FitronTP.exe to \Program Files\FitronTP\FitronTP.exe No update of Service.exe available Copy FitronTProtocols.dll to \Program Files\FitronTP\FitronTPProtocols.dll Copy FitronTPKernel.dll to \Program Files\FitronTP\FitronTPFrotocols.dll Copy FitronTP.WindowsCE.asmmeta.dll to \Program Files\FitronTP\FitronTP.FitronTP.WindowsCE.asmmeta.dll No update of LanguageTexts.txt available Update done (c) 2013 by Fiege Electronic GmbH	ronTP Update
Status: Copy FitronTP.exe to \Program Files\FitronTP\FitronTP.exe No update of Service.exe available Copy Hardware.dll to \Program Files\FitronTP\Hardware.dll Copy FitronTPProtocols.dll to \Program Files\FitronTP\Fi	Installed version: 1.0.3.0 Source path: \Program Files\FitronTP\Update Destination path: \Program Files\FitronTP
Copy FiltronTP.exe to VProgram Files\FiltronTP\FiltronTP.exe No update of Service.exe available Copy Hardware.dll to Vprogram Files\FiltronTP\FiltronTP\FiltronTP\FiltronTPProtocols.dll Copy FiltronTPKernel.dll to Vprogram Files\FiltronTP\Filtron	Status:
(c) 2013 by Fiege Electronic GmbH	Copy FitronTP.exe to \Program Files\FitronTP\FitronTP.exe No update of Service.exe available Copy Hardware.dll to \Program Files\FitronTP\Hardware.dll Copy FitronTPProtocols.dll to \Program Files\FitronTP\FitronTP\romagnet.dll Copy FitronTPRemeI.dll to \Program Files\FitronTP\FitronTPKernel.dll Copy FitronTP.WindowsCE.asmmeta.dll to \Program Files\FitronTP\FitronTP\FitronTP.WindowsCE.asmmeta.dll No update of LanguageTexts.txt available Update done
start Undate Exit	(c) 2013 by Fiege Electronic GmbH

Nach dem Update können Sie das Fenster durch Drücken des Buttons mit der Beschriftung "**Exit**" verlassen. Das Gerät startet nun mit der neuen Softwareversion. Die Software Version wird am Gerät unten links am Bildschirm angezeigt.



After the start you will see the new software version on the left side of the screen.

Die vollständige Version ist hier 2.2.0.0 (Hardware Version 1, Firmware Version 19)